Hitec 2.4 GHz Module and Receiver Firmware Update Manual

- **1.** HPP-22 Download and Installation Instructions
- 2. SPECTRA 2.4 Firmware Upgrade Procedure
- 3. Optima 7 & 9 Firmware Upgrade Procedure

HPP-22 Software Installation

1. Download the latest version of the HPP-22 software from the Hitec website

The HPP-22 and PC Software program are required to update the firmware in Spectra 2.4 Module and Optima receivers.

Go to the website as linked below:

http://www.hitecrcd.com/support/hitec-usa-downloads/software.html

2. Before installing the new HPP-22 Software you must do the following: WARNING – Failure to do follow these steps will result in interoperability issues

- A. Uninstall any previous versions of the HPP-22 Software
- B. If using Anti-Virus software turn it off for the install
- C. If Using Windows 7 or Windows Vista OS you need to run the program as an administrator or turn your User Account Control off.

3. Installing HPP-22 PC program

Please double click on the icon as you see below on the left. Select your preferred language.



H	PP-22	V1.02(8) Installation
	<u>I</u> ST	English
		OK Cancel

4. Follow the steps as shown:



🖟 HPP-22 V1.02(8) Installation		🖟 HPP-22 V1.02(8) Installation
Choose Install Location Choose the folder in which to install HPP-22.		Select shortcuts Choose a Start Menu Folder for the HPP-22 shortcuts.
Setup will install HPP-22 in the following folder. To install in a different folder, click Browse and select another folder. Click Next to continue. At least 20.95 Mb of free disk space is required.	٢	Select the Start Menu folder in which you would like to create the program's shortcuts. You can also enter a name to create a new folder. Hitecrcd
C: WProgram Files WHitecrcd WHPP-22 Browse		Hitecred X-driven
Copyright ?2009, Hitecrcd		Do not create shortcuts Copyright ?2009, Hitecrcd
IF HPP-22 V1.02(8) Installation		BHPP-22 V1.02(8) Installation
Select shortcuts Select additional shortcuts.		Ready to Install Setup is now ready to begin installing HPP-22 on your computer.
Select any additional shortcuts for HPP-22 that you would like created by the installation:		Click Install to continue with the installation, or click Back if you want to review or change any settings.
	€	Destination folder: C:\\Program Files\\Hitecrcd\\HPP-22 Start Menu Folder: Hitecrcd
Create a Desktop icon		Additional shortcuts: Create a Desktop icon Create shortcut in start menu
Copyright ?2009, Hitecrcd		Copyright ?2009, Hitecred < Back Cancel





SPECTRA 2.4 Module Firmware Upgrade Procedure

1. Program Operation

Launch the HPP-22 Software program by clicking on the HPP-22 HPP-22 icon



list*

2. Connection Sequence & Firmware Version Change

Click on the **"Upgrade Mode"** icon and **connect the cable** between HPP-22 and **Spectra 2.4 Module**, in the following sequence

- A. Connect one side of a 3-pin connector to the HPP-22 P1 port.
- B. Connect the other side of the connector to the DATA port of the module
- C. Turn on the Transmitter, (touch "YES" to transmit in the Aurora 9).



D. When the connection is successfully done, you will see the window shown below. Click on the **"Upgrade"** icon to update the firmware version of your **SPECTRA 2.4** Module.



E. Select the version you want to install and click "YES."



If everything is connected properly, the upgrade process will begin as shown.



When the firmware version change is complete, a small notification window will pop up to inform you that the version change has been completed successfully. Click **"OK"**. Now the system will take you to the **SPECTRA 2.4** Setup home screen, where you can see your current firmware version in the setup window.



When the upgrade process is complete, unplug all the cables and reboot the system by powering it off momentarily and turning it back on.

WARNING

After the firmware upgrade, you must perform a range check and full ground check before the first flight.

OPTIMA 7 & 9 Receiver Firmware Upgrade Procedure

OPTIMA 6 Note: The full telemetry and LBW functions are not available in Optima 6 or Optima 6 Lite.

Click on the HPP-22 icon on the Desktop.







*Select **"Receiver"→"OPTIMA"** from the list*

1. Connect Sequence & Change Firmware Version

- A. Run the HPP-22 PC program and connect the HPP-22 to the PC using the Mini-B/USB cable.
- B. Use the 3-pin cable to connect P1 port of HPP-22 and the DATA port of OPTIMA 7 or 9 receiver.
- C. Plug in a 4/5 cell NiMH/NiCad battery to the BAT port to turn on the receiver power.





* Note:

When connected properly, the RED and BLUE LED's on the receiver will start to blink. If the LED's don't blink, disconnect the battery power cable from the receiver momentarily then plug it back in.

D. When all the items are connected properly you will see window below. Click on the **"Upgrade"** icon in the center.



E. Select the firmware version from the list and select yes to continue





If everything is connected properly, the upgrade process will begin as shown.

When the firmware version change is complete, a small notification window will pop up to inform you that the version change has been completed successfully. Click **"OK".** Now the system will take you to the **Optima Receiver** Setup home screen, where you can see your current firmware version in the setup window.



When update is complete, a notification window will pop up notifying you that the version change has been completed successfully. Click **"OK**". Now the system will take you to **Optima Receiver Setup** home screen, where you can see your **current firmware version** in the setup window. Now that the upgrade process is complete, unplug all cables and reboot the receiver by momentarily disconnecting the power and turning it back

Warning! After the firmware upgrade, perform the range check and full ground check before the first flight.